Virtual Memory II



COMP3231 04s1

TLB Recap

- Fast associative cache of page table entries
 - Contains a subset of the page table
 - What happens if required entry for translation is not present (a *TLB miss*)?



COMP3231 04s1

s1 2

TLB Recap

- TLB may or may not be under OS control
 - Hardware-loaded TLB
 - On miss, hardware performs PT lookup and reloads TLB
 - Example: Pentium
 - Software-loaded TLB
 - On miss, hardware generates a TLB miss exception, and exception handler reloads TLB
 - Example: MIPS



COMP3231 04s1

3

0xFFFFFFF R3000 TLB kseg2 Handling 0xC0000000 TLB refill is handled by kseg1 software 0xA0000000 - An exception handler kseq0 TLB refill exceptions 0x80000000 accessing kuseg are expected to be frequent CPU optimised for handling kuseg TLB refills by having kuseg a special exception handler just for TLB refills THE UNIVERSITY OF NEW SOUTH WALES 0x00000000

Exception Vectors Program "segment" Physical Description address Address 0x8000 0000 kseg0 0x0000 0000x0 TLB miss on kuseg reference only. 0x8000 008x0 0x0000 0080 All other exceptions. Uncached alternative kuseg TLB miss entry point (used if SR bit BEV set). 0xbfc0 0100 kseg1 0x1fc0 0100 alternative for all other , used if SR bit BEV set). 0xbfc0 0180 kseg1 Special exception 0xbfc0 0000 kseq1 exception". vector for kuseg ors) for R30xx family Table 4.1. Reset and ex TLB refills COMP3231 04s1 5 THE UNIVERSITY OF NEW SOUTH WALES

Special Exception Vector · An example routine Can be optimised for TLB mfc0 k1,C0 CONTEXT refill only mfc0 k0,C0_EPC # mfc0 delay - Does not need to check the # slot exception type lw k1,0(k1) # may double - Does not need to save any # fault (k0 = orig EPC) registers nop · It uses a specialised mtc0 k1,C0_ENTRYLO assembly routine that only nop uses k0 and k1. tlbwr - Does not check if PTF jr k0 exists · Assumes virtual linear rfe array COMP3231 04s1 6 THE UNIVERSITY OF NEW SOUTH WALES

MIPS VM Related Exceptions

- TLB refill
 - Handled via special exception vector
 - Needs to be very fast
- · Others handled by the general exception vector
 - TLB Mod
 - · TLB modify exception, attempt to write to a read-only page
 - TLB Load
 - · Attempt it load from a page with an invalid translation
 - TLB Store
 - · Attempt to store to a page with an invalid translation
 - Note: these can be slower as they are mostly either caused by an error, or non-resident page.
 - We never optimise for errors, and page-loads from disk dominate the fault resolution cost.



COMP3231 04s1

7

c0 Registers

- c0 EPC
 - The address of where to restart after the exception
- c0_status
 - Kernel/User Mode bits, Interrupt control
- c0_cause
 - What caused the exception
- c0_badvaddr
 - The address of the fault



COMP3231 04s1

31 04s1 8

The TLB and EntryHi,EntryLo

EntryHi EntryLo

c0 Registers

Used to read and write individual TLB entries

> THE UNIVERSITY OF NEW SOUTH WALES


Each TLB entry contains

- EntryHi to match page# and ASID
- •EntryLo which contains frame# and protection

COMP3231 04s1

EntryHi EntryLo EntryHi EntryLo

TLB



c0 Index Register

- · Used as an index to TLB entries
 - Single TLB entries are manipulated/viewed through EntryHi and EntryLo0
 - Index register specifies which TLB entry to change/view



COMP3231 04s1


Special TLB management Instructions


- TLBR
 - TLB read
 - EntryHi and EntryLo are loaded from the entry pointer to by the index register.
- TLBP
 - TLB probe
- Set EntryHi to the entry you wish to match, index register is loaded with the index to the matching entry
- TLBWR
 - Write EntryHi and EntryLo to a psuedo-random location in the TLB
- TLBWI
 - Write EntryHi and EntryLo to the location in the TLB pointed to by the Index register.




11


COMP3231 04s1






Outline of TLB miss handling • Software does: - Look up PTE corresponding to the faulting address - If found: • load c0_EntryLo with translation • load TLB using TLBWR instructions • return from exception - Else, page fault • The TLB entry (i.e. c0_EntryLo) can be: - created on the fly, or - stored completely in the right format in page table







Demand Paging/Segmentation

- With VM, only parts of the program image need to be resident in memory for execution.
- · Can swap presently unused pages/segments to disk
- · Reload non-resident pages/segment on demand.
 - Reload is triggered by a page or segment fault
 - Faulting process is blocked and another scheduled
 - When page/segment is resident, faulting process is restarted
 - May require freeing up memory first
 - · Replace current resident page/segment
 - · How determine replacement "victim"?
 - If victim is unmodified ("clean") can simply discard it
 - . This is reason for maintaining a "dirty" bit in the PT



COMP3231 04s1

19

- Why does demand paging/segmentation work?
 - Program executes at full speed only when accessing the resident set.
 - TLB misses introduce delays of several microseconds
 - Page/segment faults introduce delays of several milliseconds
 - Why do it?
- Answer
 - Less physical memory required per process
 - · Can fit more processes in memory
 - · Improved chance of finding a runnable one
 - Principle of locality



COMP3231 04s1

20

Principle of Locality

- An important observation comes from empirical studies of the properties of programs.
 - Programs tend to reuse data and instructions they have used recently.
 - 90/10 rule
 - "A program spends 90% of its time in 10% of its code"
- We can exploit this locality of references
- An implication of locality is that we can reasonably predict what <u>instructions</u> and <u>data</u> a program will use in the near future based on its accesses in the recent past.



COMP3231 04s1

23


- Two different types of locality have been observed:
 - Temporal locality: states that recently accessed items are likely to be accessed in the near future.
 - Spatial locality: says that items whose addresses are near one another tend to be referenced close together in time.



COMP3231 04s1

22

Locality In A Memory-Reference Pattern




Working Set

- The pages/segments required by an application in a time window (Δ) is called its memory working set.
- · Working set is an approximation of a programs' locality
 - if Δ too small will not encompass entire locality.
 - if Δ too large will encompass several localities.
 - if $\Delta = \infty \Rightarrow$ will encompass entire program.
 - Δ's size is an application specific tradeoff
- System should keep resident at least a process's working set
 - Process executes while it remains in its working set
- · Working set tends to change gradually
 - · Get only a few page/segment faults during a time window
 - Possible to make intelligent guesses about which pieces will be needed in the future

 May be able to pre-fetch page/segments
 THE UNIVERSITY OF NEW SOUTH WALES
 COMP3231 04s1

segments Is1




Thrashing

- CPU utilisation tends to increase with the degree of multiprogramming
 - number of processes in system
- Higher degrees of multiprogramming less memory available per process
- Some process's working sets may no longer fit in RAM
 Implies an increasing page fault rate
 - Eventually many processes have insufficient memory
 - Can't always find a runnable process
 - Decreasing CPU utilisation
 - System become I/O limited
- · This is called thrashing.



COMP3231 04s1

26



Recovery From Thrashing

- In the presence of increasing page fault frequency and decreasing CPU utilisation
 - Suspend a few processes to reduce degree of multiprogramming
 - Resident pages of suspended processes will migrate to backing store
 - More physical memory becomes available
 - Less faults, faster progress for runnable processes
 - Resume suspended processes later when memory pressure eases




COMP3231 04s1

28

30

What is the difference?



COMP3231 04s1

THE UNIVERSITY OF NEW SOUTH WALES 29

VM Management Policies

- Operation and performance of VM system is dependent on a number of policies:
 - Page table format (my be dictated by hardware)
 - Multi-level
 - Hashed
 - Page size (may be dictated by hardware)
 - Fetch Policy

THE UNIVERSITY OF NEW SOUTH WALES

- Replacement policy
- Resident set size
 - Minimum allocation
 - Local versus global allocation
- Page cleaning policy
- Degree of multiprogramming

COMP3231 04s1

Page Size

Increasing page size

- × Increases internal fragmentation
 - reduces adaptability to working set size
- ✓ Decreases number of pages
 - · Reduces size of page tables
- ✓ Increases TLB coverage
 - Reduces number of TLB misses
- × Increases page fault latency
 - · Need to read more from disk before restarting process
- ✓ Increases swapping I/O throughput
- Small I/O are dominated by seek/rotation delays
- Optimal page size is a (work-load dependent) trade-off.



COMP3231 04s1

Atlas	512 words (48-bit)
Honeywell/Multics	1K words (36-bit)
IBM 370/XA	4K bytes
DEC VAX	512 bytes
IBM AS/400	512 bytes
Intel Pentium	4K and 4M bytes
ARM	4K and 64K bytes
MIPS R4000	4k – 16M bytes in powers of 4
DEC Alpha	8K - 4M bytes in powers of 8
UltraSPARC	8K – 4M bytes in powers of 8
PowerPC	4K bytes + "blocks"
Intel IA-64	4K – 256M bytes in powers of 4



COMP3231 04s1

32

Page Size

- Multiple page sizes provide flexibility to optimise the use of the TLB
- Example:
 - Large page sizes can be use for code
 - Small page size for thread stacks
- Most operating systems support only a single page size
 - Dealing with multiple page sizes is hard!



COMP3231 04s1


Fetch Policy

- Determines when a page should be brought into memory
 - Demand paging only loads pages in response to page faults
 - · Many page faults when a process first starts
 - Pre-paging brings in more pages than needed at the moment
 - · Improves I/O performance by reading in larger chunks
 - · Pre-fetch when disk is idle
 - · Wastes I/O bandwidth if pre-fetched pages aren't used
 - Especially bad if we eject pages in working set in order to pre-fetch unused pages.
 - · Hard to get right in practice.



COMP3231 04s1

34



Replacement Policy

- Which page is chosen to be tossed out?
 - Page removed should be the page least likely to be references in the near future
 - Most policies attempt to predict the future behaviour on the basis of past behaviour
- Constraint: locked frames
 - Kernel code
 - Main kernel data structure
 - I/O buffers
 - Performance-critical user-pages (e.g. for DBMS)
- Frame table has a lock bit



COMP3231 04s1

Optimal Replacement policy

- · Toss the page that won't be used for the longest
- · Impossible to implement
- · Only good as a theoretic reference point:
 - The closer a practical algorithm gets to optimal, the
- Example:
 - Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
 - Four frames
 - How many page faults?



COMP3231 04s1

37

FIFO Replacement Policy

- · First-in, first-out: Toss the oldest page
 - Easy to implement
 - Age of a page is isn't necessarily related to usage
- · Example:
 - Reference string: 1,2,3,4,1,2,5,1,2,3,4,5
 - Four frames
 - How many page faults?
 - Three frames?



COMP3231 04s1

38

Belady's Anomaly

 More frames does not imply fewer page faults

THE UNIVERSITY OF NEW SOUTH WALES

COMP3231 04s1

Least Recently Used (LRU)

- Toss the least recently used page
 - Assumes that page that has not been referenced for a long time is unlikely to be referenced in the near future
 - Will work if locality holds
 - Implementation requires a time stamp to be kept for each page, updated on every reference
 - Impossible to implement efficiently
 - Most practical algorithms are approximations of LRU



COMP3231 04s1


40

Clock Page Replacement

- · Clock policy, also called second chance
 - Employs a usage or reference bit in the frame table.
 - Set to one when page is used
 - While scanning for a victim, reset all the reference bits
 - Toss the first page with a zero reference bit.



COMP3231 04s1






Figure 8.16 Example of Clock Policy Operation

Issue

- How do we know when a page is referenced?
- · Use the valid bit in the PTE:
 - When a page is mapped (valid bit set), set the reference bit
 - When resetting the reference bit, invalidate the PTE entry
 - On page fault
 - Turn on valid bit in PTE
 - · Turn on reference bit
- We thus simulate a reference bit in software



COMP3231 04s1

44

Performance

- It terms of selecting the most appropriate replacement, they rank as follows
 - 1. Optimal
 - 2. LRU
 - 3. Clock
 - 4. FIFO
- Note there are other algorithms (Working Set, WSclock, Ageing, NFU, NRU)
 - We don't expect you to know them in this course



COMP3231 04s1

Resident Set Size

- How many frames should each process have?
 - Fixed Allocation
 - Gives a process a fixed number of pages within which to execute.
 - When a page fault occurs, one of the pages of that process must be replaced.
 - · Achieving high utilisation is an issue.
 - Some processes have high fault rate while others don't use their allocation.
 - Variable Allocation
 - Number of pages allocated to a process varies over the lifetime of the process



COMP3231 04s1

46


- · Variable Allocation, Global Scope
 - Easiest to implement
 - Adopted by many operating systems
 - Operating system keeps global list of free frames
 - Free frame is added to resident set of process when a page fault occurs
 - If no free frame, replaces one from any process

Variable Allocation, Local Scope

- Allocate number of page frames to a new process based on
 - Application type
 - Program request
 - Other criteria (priority)
- When a page fault occurs, select a page from among the resident set of the process that suffers the page fault
- Re-evaluate allocation from time to time!



Page-Fault Frequency Scheme



- · Establish "acceptable" page-fault rate.
 - If actual rate too low, process loses frame.
 - If actual rate too high, process gains frame.



COMP3231 04s1

49

51

Cleaning Policy

- Observation
 - Clean pages are much cheaper to replace than dirty pages
- Demand cleaning
 - A page is written out only when it has been selected for replacement
 - High latency between the decision to replace and availability of free frame
- Precleaning
 - Pages are written out in batches (in the background, the pagedaemon)
 - Increases likelihood of replacing clean frames
 - Overlap I/O with current activity



COMP3231 04s1

50


Load Control (Degree of multiprogramming)

- · Determines the number of runnable processes
- · Controlled by:
 - Admission control
 - Only let new process's threads enter ready state if enough memory is available
 - Suspension:
 - Move all threads of some process into a special suspended state
 - Swap complete process image of suspended process to disk
- Trade-off
 - Too many processes will lead to thrashing
 - Too few will lead to to idle CPU or excessive swapping



COMP3231 04s1

Load Control Considerations



· Can use page fault frequency.



COMP3231 04s1